


T.M.G. Copier Rental

How to Install Sharp Printer on Windows


Download Driver

1. Go To [CopierRental.com](https://www.copierrental.com)


2. Open **Drivers** Tab



3. Select Printer Version From List



4. Select Operating System (It May Automatically Find It)



T.M.G. Copier Rental

How to Install Sharp Printer on Windows

5. Select First Option Under **Printer Driver (PCL6 / PS / PPD Drivers)**

Driver / SoftWare Downloads

Region: **North America**

Language of Driver/SoftWare: **US English**

Product name: **MX-4070V**

Operating System: **Windows® 11**

Change

Printer Driver

✓ **PCL6 / PS / PPD Drivers**

✓ PCL6 / PS / PPD Drivers [WHQL]

(Mar. 17, 2021)

(Jul. 28, 2025)

6. Click **Download** Button (At The Bottom Of The Page)

Install Driver And Printer

7. Run Downloaded Driver (May Be in your Downloads Folder)

8. Say **Yes** On **Making Changes To This Device**

- You May Need Your Admin Password (If It Is Not Controlled By You, Ask Your I.T. To Authenticate For You)

9. Click **Next** Through Options

10. Choose **Standard Installation**

11. Select Printer From List (Preferably IP Address - Example: 192.168.1.31)

Driver Installation

SHARP

Select a MFP to install from the list.

☐	Product name	Name	Name or IP Address	Mac Address
☐	SHARP MX-3071	5198 TMG Office	fe80::8887	AC-A8-8E-67-E1-E
☒	SHARP MX-3071	5198 TMG Office	192.168.1.31	AC-A8-8E-67-E1-E

Specify Condition...

Re-search

Back

Next

Cancel

12. Click Next Through Options

13. Print Test Page

T.M.G. Copier Rental

How to Install Sharp Printer on Windows

How To Change Default Settings

1. Go To **Printers and Scanners**
2. Select Machine (SHARP MX- “Version”)
3. Open **Printing Preferences**
4. Change Options
5. Click **Ok**